

Contest Online Score Board



Content:

1. Before set up your logger,	2
2. Win-Test,	3
3. N1MM Logger+,	8
4. WriteLog,	10
5. DXlog.net,	12
6. TR4W,	13
7. UCXlog (from v. 7.76),	14
8. QARtest,	15
9. N3FJP,	16
11. Assistance,	17
12. Donations,	18
13. Testimonials,	19

1. Before set up your logger

Before configuring your logger to post contest score online you have to register your profile on the Contest Online Score Board site by visiting the following link:

<https://contestonlinescore.com/profile/>

You can add another callsign you might have to your main account. The score could be uploaded by the main or by additional callsign by using the same password.

2. Win-Test

*** Contributed by Alex, K2BB

- Download a special posting utility:
<https://contestonlinescore.com/settings/WinTestOnlineScore.zip>
- Unpack the zipped archive
- Launch Win-test logger application
- Start the WinTestOnlineScore.exe utility
- Configure WinTestOnline Score Windows like on this picture:

Win-Test Online Score

contestonlinescore.com settings

Login VA2WA

Password *****

connection settings for Win-Test

Local IP 127.0.0.1

Use Any Local IP Address

Port 9871

contest settings

Band ALL Operators VA2WA

station settings

Country VE

CQ Zone 5 Club Contest Group du Quebec


ITU Zone 4

State / Province QC

ARRL Section QC


Save Settings

- Open Win-test program. When you create a new contest. Please Check up “Enable time distribution across the network”:




... or be sure it's checked up with the current contest.


- In Win-Test application window find out “Options” on the top level menu. Then choose “Configure Interfaces..”. Checkup “ Enable Ethernet network”:




- By right mouse click over “Summary” window fall down menu choose “Broadcasting on the network” -> Enable:



1. Click on the “Periodicity...” option and type a number of minutes wanted to upload real score data with:




- If everything OK a green bar will start movement from left to right. Also the latest upload results will appear in the monitor window:



- If it's not please check up all the three Win-test settings responsible for broadcasting and network interfaces as that describe above. Disable and enable again Ethernet network as described in p. 7

3. N1MM Logger+

- Launch the N1MM+ logger application
- Go to the Config -> Configure Ports, Mode Control, Audio, Other -> Score reporting tab




- Type the Online Score Board link to the Score Reporting Server field:

<https://contestonlinescore.com/post/>

*** Be careful and don't forget the last symbol - /. That wouldn't work without it!


- Type your callsign as Username and registered Password



- Checkup "Report Real time Score Server" and Exclude band breakdown
- Choose "Upload interval" as you wish
- Click on "OK"

4. WriteLog

- Launch the WriteLog logger application
- Go to the “Contest -> Broadcast” score menu option



- Type the Online Score Board link to the Network Address field:

<https://contestonlinescore.com/post/>

*** Be careful and don't forget the last symbol - /. That wouldn't work without it!

- Type your registered password
- Change “Upload time” to 2, 5 or other time
- Checkup “Post qso&mult breakdown also” checkbox
- Fill up the Contest form fields as shown on the picture:

Log submission details

Call used: VA2WA Location [dropdown]

Operator SINGLE-OP Overlay ROOKIE Station FIXED

Power HIGH Xmtr ONE Mode MIXED Band ALL

Assisted ASSISTED Time 24-HOURS

Club [text box]

Calls of all operators VA2WA

State/Province QC Country CANADA

Create Cabrillo File | Address for Cabrillo | Soapbox for Cabrillo | cqcontest.net Upload

Network Address: <https://contestonlinescore.com/post/> UDP Port: 9871

Password: XXXXXXXX

Active Contests: IARU-HF


Upload Post Score every: 2 min Start post qso&mult breakdown also

OK Cancel Help

- Click "OK"

5. DXlog.net


- Launch the DXlog logger application
- Go to the “Command -> Live score->Setup->Post address” menu option:



- Check up the “Use https” checkbox
- Fill up the Post address form by typing your password and https:

<https://contestonlinescore.com/post/>

*** Be careful and don't forget the last symbol - /. That wouldn't work without it!



- Be sure you have checked up “Enable auto posting” from the “Commands->Live score” menu

6. TR4W

- Launch the TR4W logger application
- By clicking combination “CTR-J” get the TR4W settings popup window
- Enter <http://post.contestonlinescore.com> as SCORE POSTING URL
- Enter <https://contestonlinescoreboard.com/scoreboard/> as SCORE READING URL
- Open Window -> “Post score” pop up window. Click “Post now” to upload your score to the server:

The screenshot shows the TR4W v.4.60.0 - 2017 CWOPS VA2WA application window. The main window displays a log of activity with columns for Band, Date, UTC, QsS, Callsign, Px, Name, QTH, Pts, M, Id, \$, D, Freq, and Op. A configuration popup window titled "Configuration commands" is open, showing a list of commands and their values. The "SCORE POSTING URL" command is highlighted, with its value set to "http://post.contestonlinescore.com/". The "SCORE READING URL" is set to "https://contestonlinescore.com/scoreboard/".

Command	Value	#	File
SAY HI ENABLE	FALSE	244	
SAY HI RATE CUTOFF	200	245	
SCORE POSTING URL	http://post.contestonlinescore.com/	246	
SCORE READING URL	https://contestonlinescore.com/scoreboard/	247	
SCP COUNTRY STRING		248	
SCP MINIMUM LETTERS	0	249	
SEND COMPLETE FOUR LETTER CA...	FALSE	250	
SERIAL PORT DEBUG	FALSE	251	
SERVER ADDRESS	LOCALHOST	252	
SERVER PASSWORD	TR4WSERVER	253	
SERVER PORT	1061	254	
SHIFT KEY ENABLE	TRUE	255	
SHORT 0	0	256	
SHORT 1	1	257	
SHORT 2	2	258	
SHORT 9	9	259	
SHORT INTEGERS	FALSE	260	Cl
SHOW DOMESTIC MULTIPLIER NAME	FALSE	261	
SHOW FREQUENCY IN LOG	TRUE	262	
SHOW TYPED CALLSIGN	TRUE	263	
SINGLE BAND SCORE	All	264	Cl
SINGLE RADIO MODE	FALSE	265	
SKIP ACTIVE BAND	FALSE	266	
SLASH MARK CHAR	/	267	
SPACE BAR HIDE CHECK ENABLE	TRUE	268	

Default:
http://cqcontest.ru/postscore.jsp

Description:

Arrow/pageup/pagedn keys or 1st letter to select item.

Modify Save (Alt+W) Save all (Alt+G) To network Exit

7. UCXlog (from v. 7.76)

- Launch the UCXlog application:
- Contest -> Work -> Score Upload option.
- Please fill up the form and checkup the marked by red options:
 - B: Contest Online Score Board
 - HTTPS

Score Upload

Upload to

- A: CQ Contest Server
- B: Contest Online Score Board

Upload now !

after every logging [v] 1 [u] min

Content Band QSOs + Points + Multipliers [v]

Last server responses:

A: 08:44:44 : OK-Full

B: 08:44:44 : OK-Full

Contest DL-DX-RTTY [v]

Category - Operator SINGLE-OP [v]

Transmitter ONE [v]

Band ALL [v]

Mode RTTY [v]

Power HIGH [v]

Assisted NON-ASSISTED [v]

Login DL7UCX [v] HTTPS

Password ***** [v] Hide window

8. QARtest

- Please follow to instructions given on the page : http://www.ik3qar.it/software/qartest_ita/

9. N3FJP

- From the contest program's menu options click Settings > Web Contest Upload Status > Other Online Score Sites.
- Enter your user info and checkup "Enable" checkbox for the upload.

Web Contest Status Uploader - Other Real Time Online Scoreboard Sites

Watching everyone's score in real time is a blast! Whether you have serious competition in mind or you are just playing casually in the contest, please create free accounts for both sites and then enable both CQContest.Net and ContestOnlineScore.com! Click Visit below to quickly visit the sites.

Click Test to test your settings. Results of the test upload will appear in this textbox. OK-Full is the desired response from both sites.

Total score, total QSOs and total multipliers will automatically upload at 3 minute intervals. A band by band breakdown is not included.

CqContest.net

User Name

Password Display

URL

Enabled

ContestOnlineScore.com

User Name

Password Display

URL

Enabled

Other

User Name

Password Display

URL

Enabled

Contest Upload Parameters

Contest	Callsign	Operator	Transmitter	Power	Assisted	Sec
CQ-WW-SSB	N3FJP	SINGLE-OP	ONE	HIGH	ASSISTED	MDC

Band	Mode	Category Overlay	Club Name
ALL	SSB	N/A	Northeast Maryland Amateur Radio Contest Society

10. Assistance

If you still have questions or need an **assistance** with your logger setup please don't hesitate to drop a message to our email address:

admin@contestonlinescore.com

If you have any **feedback or suggestions** please don't hesitate to send them to us by using our email address:

admin@contestonlinescore.com

11.Donations

We are renting our servers for the Contest Online Score Board project. We are constantly spending our time for providing technical support, working on new features and keeping track on new contests to be active on the Board. If you like our service and you wish to support us you could send a **donation** by PayPal to the email address:

admin@contestonlinescore.com

12. Testimonials:

We all love HAM Radio and contesting as an essential of our hobby. Great thanks to everyone who helped us to have this project up and running:

Gerry, W1VE,

Randy, K5ZD,

Yuri, VE3DZ

Tom, N1MM

Wayne, W5XD

Lourent, F6FVY

Martin, OK1RR

Chris 9A5K

Paolo, IK3QAR,

Ben, DL7UCX

Scott, N3FJP

And many others who kindly helped us with feedback, suggestions and donations:

Claude, VE2FK

Mats, RM2D/SM6LRR

Ken, K6MR

Rudy, N2WQ

We are open to any suggestions and ideas since we are HAM Radio community project driving by community and for the community!

73! de Contest Online Score Board team